

4

Using USB Cable (Mac)


Device Recognition (Mac)	4-2
Installing Utility Software	4-2
Installation of Utility Software	4-2
Uninstalling Utility Software	4-4

Using USB Cable (Mac)

Device Recognition (Mac)

- 1 Insert micro USB plug into Mobile Router (USIM Card installed) External Device Port
- 2 Insert USB plug of USB Cable into Mac USB Port
- 3 Press Power Key of Mobile Router for more than two seconds

Mac should recognize Mobile Router within a few seconds.



► Mobile Router may fail if Mac enters sleep mode, etc. with it connected. Remove Mobile Router before leaving a Mac unattended, etc. Mobile Router may malfunction if connected before Mac starts/restarts. Remove Mobile Router before starting or restarting Mac.


Installing Utility Software

■ Installation of Utility Software

Mobile Router driver and Utility Software are already saved. Installed programs run automatically on Macs. All screenshots and procedures based on Mac OS X 10.6.

► Do not remove Mobile Router during installation. It may cause installation failure, system malfunction or other system errors.

- 1 Power on Mac
- 2 Connect Mobile Router to Mac via USB Cable
- 3 Double-click *CD-ROM* when it appears on desktop



Using USB Cable (Mac)

- 4 Double-click **101SI Utility Installer.mpkg** to start installation




- ▶ When Utility Software is installed in Mac, uninstall it (P.4-4). Then install Utility Software.
- ▶ Make sure that only the latest Utility Software is installed before use.

- 5 "Select a Destination" dialog box appears. Select installation destination and click **Continue**



- 6 Standard Install on Mac HD dialog box appears. Click **Install**




- ▶ "Macintosh HD" is hard disk name. Name shown varies depending on the user.

Using USB Cable (Mac)

- 7 Certification appears. Enter Name and Password and click **OK**



- 8 Installation starts
- 9 When dialog box is shown as below, click **Close**



- 10 Click  to open Finder. If **101SI Utility** appears in **Application**, installation finishes

Uninstalling Utility Software

- 1 Click  to open Finder
- 2 Select **101SI Utility** and Drag & Drop **101SI Utility** to **Trash**
- 3 Drag & Drop **SEIKO101SIRoot.kext** to **Trash**

File location is "/System/Library/Extensions/SEIKO101SIRoot.kext".

- 4 Restart Mac

► After starting Utility Software, "The item "101SI Utility" can't be moved to Trash because it's open.", dialog box appears, and uninstallation is unavailable. End Utility Software and implement again.

► Restart Mac if it does not function correctly.